


# Installation Solid Edge ST6 Nodelocked-Lizenz



Gehen Sie mit einem Internetbrowser auf die Seite (ohne www.)

[www.siemens.com/gtac](http://www.siemens.com/gtac)

Klicken Sie auf „Lizenz Verwaltung“ und dann auf „aktuelle Lizenz“.




1. Geben Sie Ihren Webkey Username ein.
2. Geben Sie Ihr Webkey Password ein.
3. Klicken Sie auf „sign in“.

Haben Sie noch keinen Webkey Account oder Ihre Daten nicht mehr?


Nehmen Sie den Leitfaden zur Erstellung eines Webkey-Accounts zur Hand.

# Installation Solid Edge ST6 Nodelocked-Lizenz



The screenshot shows the Siemens License Management interface. The 'Product Activation' link is highlighted with a red box. The page includes a navigation menu, a 'Sold-To/Install' dropdown menu, and several quick links: Home, Emergency License, and Register IP Address. Below the quick links, there are instructions for selecting a license management function.

Klicken Sie auf „Product Activation“.




The screenshot shows the 'Product Activation' dialog box. The 'Product' dropdown is set to 'Solid Edge' and the 'Version' dropdown is set to '100.0'. The 'Continue' button is highlighted with a green box. The dialog includes a 'Cancel' button and a copyright notice at the bottom.

1. Wählen Sie das eingesezte Produkt.

2. Wählen Sie die Version, die verwendet werden soll (V103 steht für Version ST3; V106 steht für Version ST 6).

3. Bestätigen Sie Ihre Auswahl mit einem Klick auf „Continue“.

# Installation Solid Edge ST6 Nodelocked-Lizenz



**SIEMENS** → siemens.com  
 US Site United States

Siemens PLM Software  
 About Us Products Industry Solutions Partners Training & Support

About LM  
 GTAC  
 FTP Server  
 Home

Sold-To/Install: 0001007711  
 PBU CAD-Systeme GmbH  
 Robert-Bosch-Straße 8  
 Aichach 86551

**License Management**

1 Home 2 Emergency License 3 Register IP Address

**Product Activation**

Step 1: Click Create New Machine to activate a machine and assign products to it.  
 Step 2: Click Generate License File to obtain your license after you have activated your machine(s). This license file will work on any one of the machines you have.  
 Step 3: To edit the licensing of an existing machine click on **5** ne name.

4 Create New Machine 5 Generate License File 6 Cancel

**7**

Product ID	Description	Maintenance Expiration	License Type	Available Quantity
SE289-GER	Solid Edge - German	31/01/2010	DEMO	000000001
SEDEMO	Solid Edge Demo	31/01/2010	DEMO	000000001
SEDEMO	Solid Edge Demo	31/01/2010	DEMO	000000007

Collapse Detail

**8**


- \*Machine: TestMoers01(08732737)
- \*Machine: aaaaaaaaa(08732737)
- \*Machine: fletdt(08732737)
- \*Machine: meiner(08732737)
- \*Machine: neu1(08732737)
- \*Machine: test500(123789DD)
- \*Machine: Test(1C03A2C7)
- \*Machine: Testrechner(1C03A2C7)
- \*Machine: test999(1C03A2C7)
- \*Machine: Katrin(40FF88DC)
- \*Machine: notebook(40FF88DC)
- \*Machine: testtesttest(40FF88DC)
- \*Machine: Dietmar(6457FB20)
- \*Machine: Schwarz(6457FB20)
- \*Machine: links(685D3179)
- \*Machine: Testmaschine(886500DE)
- \*Machine: Klein(9C2C544)
- \*Machine: iiiiii(80DAFFC)
- \*Machine: testtje(B8CE174D)
- \*Machine: Test(BC9D5362)
- \*Machine: wma(BCF2E692)
- \*Machine: Montagerechner(D65613DB)

Übersicht der Lizenzmanagement-Seite

1. Auswahlbutton Home
2. Emergency License
3. Register IP-Address
4. Create New Machine
5. Generate License File
6. Cancel
7. Liste noch keinem Rechner zugewiesener Lizenzen
8. Liste der erstellten Rechner

Bitte klicken Sie als nächsten Schritt Button 4: Create New Machine, um einen Rechner anzulegen, dem man dann eine Lizenz zuweisen kann.

# Installation Solid Edge ST6 Nodelocked-Lizenz



**Product Activation**

Step 1: Enter the name of machine you want to activate. The machine name is used to identify this machine later should you want to edit it. Enter a name that is memorable and identifies the machine at your site.

Step 2: Enter the disk serial number (volume id) without the dash of the machine. The disk serial number is shown in the upper right corner of the Solid Edge License Utility delivered with Solid Edge. It is also shown as the Volume Serial Number if you run the vol.c command from a command prompt window.

Step 3: Click Create to create the machine.

Step 4: Click Assign Products to add products to the new machine.

Note: The Solid Edge Composite ID (SE CID) is required for ST4 license files. If you are connected using the machine you are activating you can click Get Number to retrieve your SE CID value. To obtain the value manually download and run the SE CID utility on the machine you are activating. The utility can be downloaded from the Siemens PLM FTP Server

Machine Name\*  **1**


activation3.secid\*  Get Number **2**

\*Required field

**3**

- 1. Vergeben Sie einen x-beliebigen Rechnernamen.**
- 2. Geben Sie die Solid Edge CID des Rechners an, für den diese Lizenzierung ange-dacht ist. Oder Auf „Get Number“ klicken.**
- 3. Klicken Sie auf Create.**

Falls Sie diese Nummer nicht zur Hand haben, nehmen Sie den Leitfaden zur Ermittlung der Solid Edge Composite ID zur Hand.



Create New Machine Generate License File Cancel

Product ID	Description	Maintenance Expiration	License Type	Available Quantity
SE289-GER	Solid Edge - German	31/01/2010	DEMO	000000001
SEDEMO	Solid Edge Demo	31/01/2010	DEMO	000000001
SEDEMO	Solid Edge Demo	31/01/2010	DEMO	000000007

Collapse Detail

\*Machine: TestMoers01(08732737)

\*Machine: aaaaaaaaa(08732737)

\*Machine: fteidt(08732737)

\*Machine: meiner(08732737)

\*Machine: neu1(08732737)

\*Machine: test500(123789DD)


\*Machine: Test(1C03A2C7)

\*Machine: Testrechner(1C03A2C7)

\*Machine: test999(1C03A2C7)

Nach dem der Rechner erstellt wurde kann dieser in der **Liste der erstellten Rechner** ausgewählt werden.

# Installation Solid Edge ST6 Nodelocked-Lizenz



**SIEMENS** → siemens.com  
US Site United States

Siemens PLM Software  
About Us Products Industry Solutions Partners Training & Support

About LM  
GTAC  
FTP Server  
Home

Solid-To/Install: 0001007711  
FBU CAD-Systeme GmbH  
Robert-Bosch-Straße 8  
Aichach 86551

TAPPING THE POWER OF PLM  
**License Management**

Quick Links  
Home Emergency License Register IP Address

**Product Activation**

Select the product(s) to Remove from this machine. To assign Items to this machine click the Assign Products tab.  
Note: To successfully license and run your applications, make sure that you have selected a single standalone product for your machine. Standalone products are Solid Edge Classic, Foundation, Design and Drafting and Insight.


Machine : Testrechner(1C03A2C7)

**Assign Products** Remove Products

Product ID	Description	Maintenance Expiration	License Type	Available Quantity	Remove One
There are no products currently assigned to this machine.					

Finish

Wählen Sie „Assign Products“.



**SIEMENS** → siemens.com  
US Site United States

Siemens PLM Software  
About Us Products Industry Solutions Partners Training & Support

About LM  
GTAC  
FTP Server  
Home

Solid-To/Install:  
PBU CAD-Systeme GmbH  
Robert-Bosch-Straße 8  
Aichach 86551

TAPPING THE POWER OF PLM  
**License Management**

Quick Links  
Home Emergency License Register IP Address

**Product Activation**

Select the product(s) to assign to this machine. To remove items from this machine click the Remove Products tab.  
Note: To successfully license and run your applications, make sure that you have selected a single standalone product for your machine. Standalone products are Solid Edge Classic, Foundation, Design and Drafting and Insight.

Machine : Testrechner(1C03A2C7)

**Assign Products** Remove Products


Product ID	Description	Maintenance Expiration	License Type	Available Quantity	Assign One	Product Assign on Testrechner(1C03A2C7)
SE209-CER	Solid Edge - German	31/01/2010	DEMO	000000001	Assign 0	1
SEDEMO	Solid Edge Demo	31/01/2010	DEMO	000000001	Assign 0	
SEDEMO	Solid Edge Demo	31/01/2010	DEMO	000000007	Assign 0	

2 Finish

1. Wählen Sie die Lizenzen und Zusatzmodule die dem Rechner zugewiesen werden sollen.

2. Bestätigen Sie Ihre Auswahl mit Finish.

# Installation Solid Edge ST6 Nodelocked-Lizenz



**Product Activation**

Step 1 : Click Create New Machine to activate a machine and assign products to it.  
 Step 2 : Click Generate License File to obtain your license after you have activated your machine(s). This license file will work on any one of the machines you have activated.  
 Step 3 : To edit the licensing of an existing machine click on the machine name.

Buttons:    **2**

Product ID	Description	Maintenance Expiration	License Type	Available Quantity
SEDEMO	Solid Edge Demo	31/01/2010	DEMO	000000001
SEDEMO	Solid Edge Demo	31/01/2010	DEMO	000000007

**Machine: test500(123789DD)**  
 SE289-GER Solid Edge - German 31/01/2010 DEMO 000000001 **1**

\*Machine: TestMoers01(08732737)  
 \*Machine: aaaaaaaaa(08732737)  
 \*Machine: fletdt(08732737)  
 \*Machine: meiner(08732737)  
 \*Machine: neu1(08732737)  
 \*Machine: Test(1C03A2C7)  
 \*Machine: Testrechner(1C03A2C7)  
 \*Machine: test999(1C03A2C7)

**1. Hier werden Ihnen nun die Rechner mit den zugewiesenen Lizenzen angezeigt.**

**2. Um die Lizenz nun zu erstellen, klicken Sie auf Generate License File und speichern diese ab.**

Wenn Sie mehrere Rechner erstellen und diesen Lizenzen zuweisen wollen, wiederholen Sie die oben genannten Schritte und erstellen Sie erst am Ende die Lizenz.

Diese kann dann auf jedem in der Liste aufgeführten Rechner verwendet werden.